

Understanding the Durbin-Watson Test: A Guide to Interpreting Critical Values for Time-Series Analysis

Authored by
Mohammed loot

November 9, 2025

RECOMMENDED CITATION

Mohammed loot (2025). *Understanding the Durbin-Watson Test: A Guide to Interpreting Critical Values for Time-Series Analysis*. PSYCHOLOGICAL STATISTICS. Retrieved from <https://statistics.arabpsychology.com/?p=14438>

The Foundation of Time-Series Analysis: Introducing the Durbin-Watson Test

The [Durbin-Watson Test](#) is an indispensable diagnostic tool used primarily within [regression analysis](#) to rigorously assess the existence of [autocorrelation](#), often referred to as serial correlation, among the residuals of a time-series dataset. Conceptualized and developed by statisticians James Durbin and Geoffrey Watson in the early 1950s, this test directly addresses one of the core assumptions underlying classical linear regression models: the critical requirement that error terms must be independent. When implementing the widely utilized **Ordinary Least Squares (OLS)** method, it is fundamentally assumed that the errors linked to any single observation bear no correlation with the errors of any other observation. The violation of this crucial independence assumption, particularly common in data collected sequentially over time (e.g., economic or financial data), severely compromises the reliability of statistical inference. Specifically, it leads to biased standard errors and potentially misleading t-statistics, even though the coefficient estimates themselves may remain unbiased. Consequently, executing the Durbin-Watson test is an essential preliminary step for validating the structural integrity and statistical robustness of any time-series regression model before drawing substantive conclusions.

The central mission of the Durbin-Watson statistic is to quantify the strength and nature of the linear relationship between the current residual (e_t) and the residual from the immediately preceding time period (e_{t-1}). The presence of **positive autocorrelation**, where a positive error is typically followed by another positive error, is a pervasive issue in empirical economic and financial time series. Conversely, **negative autocorrelation**, which is far less common, implies that positive errors tend to be succeeded by negative errors, indicating an oscillatory pattern in the residuals. If this test detects statistically significant autocorrelation, researchers must abandon standard OLS inference and employ sophisticated statistical adjustments or alternative modeling techniques. These alternatives often include methods such as [Generalized Least Squares \(GLS\)](#) or the strategic inclusion of lagged dependent variables, all aimed at restoring the validity and efficiency of the model's coefficients and hypothesis tests. The test statistic itself, conventionally denoted by 'd', is meticulously derived from the calculated [residuals](#) generated by the fitted regression model, culminating in a single numerical value that succinctly summarizes the degree of serial correlation present in the model's error structure.

Interpreting the output of the Durbin-Watson test necessitates comparing the calculated 'd' statistic against a predefined set of critical values. These critical values are uniquely determined by several specific characteristics of the model under examination. These defining factors include the **sample size (n)**, the total **number of independent variables (k)** utilized in the model (excluding the intercept), and the chosen **level of significance (α)**. Unlike many conventional statistical tests that rely on a single critical value to define the rejection region, the Durbin-Watson test requires two boundary values: a lower bound (d_L) and an upper bound (d_U). These two critical bounds serve to delineate three distinct zones: a region of definite positive autocorrelation,

a region of non-autocorrelation (independence), and an indeterminate or inconclusive zone. This complex bounding structure reflects the inherent mathematical difficulty in testing for serial correlation, especially since the true population errors are unobservable and must be estimated from the available sample data.

The Calculation and Interpretation of the Durbin-Watson Statistic

The core concept of autocorrelation is fundamental to grasping why the Durbin-Watson test is essential. When regression residuals exhibit correlation over time, it provides strong evidence that the OLS model has failed to capture some systematic, time-dependent pattern within the data. This failure often results in standard errors that are systemically understated. If the calculated standard errors are artificially small, the corresponding t-statistics become inflated, dramatically increasing the risk of making a Type I error--the incorrect rejection of the [null hypothesis](#). For example, in the presence of strong positive autocorrelation, the effective number of truly independent observations is significantly reduced. This reduction leads to an overly optimistic calculation of the variance of the coefficient estimates, potentially causing researchers to assign undue confidence to results that are, in fact, statistically tenuous.

The derivation of the Durbin-Watson statistic is elegantly engineered to precisely quantify this sequential dependence. The statistic 'd' is mathematically defined as the ratio of the sum of squared differences between successive residuals to the sum of the squared residuals themselves. By definition, the statistic 'd' is constrained to fall within the range of 0 to 4. A value of 'd' that is precisely or very close to 2 signifies that the residuals are completely uncorrelated, perfectly satisfying the OLS assumption of independent errors. Conversely, a value approaching 0 indicates severe **positive autocorrelation**, meaning that the residual at time t is highly correlated with its predecessor at time $t-1$. Conversely, a value near 4 points to extremely strong **negative autocorrelation**, an outcome that, while less frequent in economic modeling, is equally detrimental to the validity of statistical inference.

The necessity of using specific critical value tables stems from the non-standard and complex distribution of the Durbin-Watson statistic. The exact probability distribution of 'd' is intrinsically dependent on the specific values of the independent variables (the X matrix), which inherently varies across different regression models. To overcome this analytical challenge, Durbin and Watson meticulously calculated bounds (d_L and d_U) that encompass the entire possible range of the true critical values, regardless of the specific configuration of the independent variables. These calculated bounds enable researchers to draw robust conclusions regarding the presence of autocorrelation solely based on the model's size parameters (n and k). This bounded decision framework provides a consistent and reliable method for testing across diverse applications, contingent on the data structure adhering to the sequential nature characteristic of time-series observations.

Defining the Parameters for Critical Value Lookup

The effective and accurate application of the Durbin-Watson critical value tables relies entirely on the correct determination of three essential parameters, all of which are derived directly from the fitted regression model and the chosen analytical standard. These parameters dictate the specific row and column coordinates required to extract the lower (d_L) and upper (d_U) critical bounds from the tabulated data. Any failure to correctly identify these inputs will invariably lead to the selection of incorrect critical values, resulting in erroneous conclusions regarding the presence or absence of serial correlation.

The determination process involves:

Sample Size (n): This parameter represents the total number of observations utilized in the regression model. In the context of time-series analysis, this is equivalent to the number of time periods analyzed. This value dictates the specific row index that must be used within the critical value table.

Number of Independent Variables (k): This refers strictly to the count of predictor variables included in the model, with the explicit exclusion of the intercept term (or constant term). It is crucial to remember that the constant term is deliberately not counted as an independent variable when determining the value of ' k ' for Durbin-Watson table consultation. This parameter dictates the appropriate column index.

Alpha Level (α): This is the predetermined and established level of statistical significance. Common practice dictates setting α at either 0.05 (5%) or 0.01 (1%). The choice of the alpha level is critical because it determines which specific critical value table is consulted, as the calculated bounds shift depending on the required level of confidence and the associated risk tolerance for Type I errors.

Once these three parameters (n , k , and α) have been precisely identified, the researcher must locate the corresponding row (based on n) and column (based on k) within the table corresponding to the chosen α level. The resulting intersection yields the required pair of critical bounds, d_L and d_U . These bounds are absolutely indispensable for defining the rigorous decision regions necessary to test the [null hypothesis](#) that there is no positive autocorrelation of the first order. The provided images below offer comprehensive tables spanning various combinations of these parameters, thereby enabling researchers to quickly find the necessary critical values for the two most common significance levels.

Durbin-Watson Critical Value Tables

The following tables furnish the necessary critical values required for conducting the [Durbin-](#)

[Watson Test](#). The first table is specifically calibrated for a highly stringent level of significance, $\alpha = 0.01$. This low threshold demands extremely strong evidence to justify the rejection of the null hypothesis of no autocorrelation. This stringent level is typically employed in situations where the consequences of mistakenly identifying autocorrelation are severe, or when analyzing highly sensitive data, such as volatile financial time series, where model stability is paramount.

$\alpha = .01$										
	k = 1		k = 2		k = 3		k = 4		k = 5	
n	dL	dU	dL	dU	dL	dU	dL	dU	dL	dU
6	0.39	1.14								
7	0.44	1.04	0.29	1.68						
8	0.5	1	0.35	1.49	0.23	2.1				
9	0.55	1	0.41	1.39	0.28	1.88	0.18	2.43		
10	0.6	1	0.47	1.33	0.34	1.73	0.23	2.19	0.15	2.69
11	0.65	1.01	0.52	1.3	0.4	1.64	0.29	2.03	0.19	2.45
12	0.7	1.02	0.57	1.27	0.45	1.58	0.34	1.91	0.24	2.28
13	0.74	1.04	0.62	1.26	0.5	1.53	0.39	1.83	0.29	2.15
14	0.78	1.05	0.66	1.25	0.55	1.49	0.44	1.76	0.34	2.05
15	0.81	1.07	0.7	1.25	0.59	1.46	0.49	1.7	0.39	1.96
16	0.84	1.09	0.74	1.25	0.63	1.44	0.53	1.66	0.44	1.9
17	0.87	1.1	0.77	1.25	0.67	1.43	0.57	1.3	0.48	1.85
18	0.9	1.12	0.8	1.26	0.71	1.42	0.61	1.6	0.52	1.8
19	0.93	1.13	0.83	1.26	0.74	1.41	0.65	1.58	0.56	1.77
20	0.95	1.15	0.86	1.27	0.77	1.41	0.68	1.57	0.6	1.74
21	0.97	1.16	0.89	1.27	0.8	1.41	0.72	1.55	0.63	1.71
22	1	1.17	0.91	1.28	0.83	1.4	0.75	1.54	0.66	1.69
23	1.02	1.19	0.94	1.29	0.86	1.4	0.77	1.53	0.7	1.67
24	1.04	1.2	0.96	1.3	0.88	1.41	0.8	1.53	0.72	1.66
25	1.05	1.21	0.98	1.3	0.9	1.41	0.83	1.52	0.75	1.65
26	1.07	1.22	1	1.31	0.93	1.41	0.85	1.52	0.78	1.64
27	1.09	1.23	1.02	1.32	0.95	1.41	0.88	1.51	0.81	1.63
28	1.1	1.24	1.04	1.32	0.97	1.41	0.9	1.51	0.83	1.62
29	1.12	1.25	1.05	1.33	0.99	1.42	0.92	1.51	0.85	1.61
30	1.13	1.26	1.07	1.34	1.01	1.42	0.94	1.51	0.88	1.61
31	1.15	1.27	1.08	1.34	1.02	1.42	0.96	1.51	0.9	1.6
32	1.16	1.28	1.1	1.35	1.04	1.43	0.98	1.51	0.92	1.6
33	1.17	1.29	1.11	1.36	1.05	1.43	1	1.51	0.94	1.59
34	1.18	1.3	1.13	1.36	1.07	1.43	1.01	1.51	0.95	1.59
35	1.19	1.31	1.14	1.27	1.08	1.44	1.03	1.51	0.97	1.59
36	1.21	1.32	1.15	1.38	1.1	1.44	1.04	1.51	0.99	1.59
37	1.22	1.32	1.16	1.38	1.11	1.45	1.06	1.51	1	1.59
38	1.23	1.33	1.18	1.39	1.12	1.45	1.07	1.52	1.02	1.58
39	1.24	1.34	1.19	1.39	1.14	1.45	1.09	1.52	1.03	1.58
46	1.25	1.34	1.2	1.4	1.15	1.46	1.1	1.52	1.05	1.58
45	1.29	1.38	1.24	1.42	1.2	1.48	1.16	1.53	1.11	1.58
50	1.32	1.4	1.28	1.45	1.24	1.49	1.2	1.54	1.16	1.59
55	1.36	1.43	1.32	1.47	1.28	1.51	1.25	1.55	1.21	1.59
60	1.38	1.45	1.35	1.48	1.32	1.52	1.28	1.56	1.25	1.6
65	1.41	1.47	1.38	1.5	1.35	1.53	1.31	1.57	1.28	1.61
70	1.43	1.49	1.4	1.52	1.37	1.55	1.34	1.58	1.31	1.61
75	1.45	1.5	1.42	1.53	1.39	1.56	1.37	1.59	1.34	1.62
80	1.47	1.52	1.44	1.54	1.42	1.57	1.39	1.6	1.36	1.62
85	1.48	1.53	1.46	1.55	1.43	1.58	1.41	1.6	1.39	1.63
90	1.5	1.54	1.47	1.56	1.45	1.59	1.43	1.61	1.41	1.64
95	1.51	1.55	1.49	1.57	1.47	1.6	1.45	1.62	1.42	1.64
100	1.52	1.56	1.5	1.58	1.48	1.6	1.46	1.63	1.44	1.65
150	1.61	1.64	1.6	1.65	1.58	1.67	1.57	1.68	1.56	1.69
200	1.66	1.68	1.65	1.69	1.64	1.7	1.63	1.72	1.62	1.73

The subsequent tables present the critical values optimized for the standard and most frequently adopted level of significance: $\alpha = 0.05$. This 5% significance level represents the most common threshold utilized in empirical research across disciplines including economics, the social sciences, and various engineering fields. It provides a balanced statistical approach aimed at minimizing the risks associated with both Type I and Type II errors. Researchers are required to meticulously cross-reference their specific sample size (n) and the count of predictor variables (k) to accurately extract the correct lower (d_L) and upper (d_U) bounds from these tabulated values. The tables are carefully organized to facilitate the rapid and accurate identification of the necessary decision thresholds across a broad spectrum of potential regression model configurations.

$\alpha = .05$										
	k = 1		k = 2		k = 3		k = 4		k = 5	
n	dL	dU	dL	dU	dL	dU	dL	dU	dL	dU
6	0.61	1.4								
7	0.7	1.36	0.47	1.9						
8	0.76	1.33	0.56	1.78	0.37	2.29				
9	0.82	1.32	0.63	1.7	0.46	2.13	0.3	2.59		
10	0.88	1.32	0.7	1.64	0.53	2.02	0.38	2.41	0.24	2.82
11	0.93	1.32	0.66	1.6	0.6	1.93	0.44	2.28	0.32	2.65
12	0.97	1.33	0.81	1.58	0.66	1.86	0.51	2.18	0.38	2.51
13	1.01	1.34	0.86	1.56	0.72	1.82	0.57	2.09	0.45	2.39
14	1.05	1.35	0.91	1.55	0.77	1.78	0.63	2.03	0.51	2.3
15	1.08	1.36	0.95	1.54	0.82	1.75	0.69	1.97	0.56	2.21
16	1.1	1.37	0.98	1.54	0.86	1.73	0.74	1.93	0.62	2.15
17	1.13	1.38	1.02	1.54	0.9	1.71	0.78	1.9	0.67	2.1
18	1.16	1.39	1.05	1.53	0.93	1.69	0.92	1.87	0.71	2.06
19	1.18	1.4	1.08	1.53	0.97	1.68	0.86	1.85	0.75	2.02
20	1.2	1.41	1.1	1.54	1	1.68	0.9	1.83	0.79	1.99
21	1.22	1.42	1.13	1.54	1.03	1.67	0.93	1.81	0.83	1.96
22	1.24	1.43	1.15	1.54	1.05	1.66	0.96	1.8	0.96	1.94
23	1.26	1.44	1.17	1.54	1.08	1.66	0.99	1.79	0.9	1.92
24	1.27	1.45	1.19	1.55	1.1	1.66	1.01	1.78	0.93	1.9
25	1.29	1.45	1.21	1.55	1.12	1.66	1.04	1.77	0.95	1.89
26	1.3	1.46	1.22	1.55	1.14	1.65	1.06	1.76	0.98	1.88
27	1.32	1.47	1.24	1.56	1.16	1.65	1.08	1.76	1.01	1.86
28	1.33	1.48	1.26	1.56	1.18	1.65	1.1	1.75	1.03	1.85
29	1.34	1.48	1.27	1.56	1.2	1.65	1.12	1.74	1.05	1.84
30	1.35	1.49	1.28	1.57	1.21	1.65	1.14	1.74	1.07	1.83
31	1.36	1.5	1.3	1.57	1.23	1.65	1.16	1.74	1.09	1.83
32	1.37	1.5	1.31	1.57	1.24	1.65	1.18	1.73	1.11	1.82
33	1.38	1.51	1.32	1.58	1.26	1.65	1.19	1.73	1.13	1.81
34	1.39	1.51	1.33	1.58	1.27	1.65	1.21	1.73	1.15	1.81
35	1.4	1.52	1.34	1.58	1.28	1.65	1.22	1.73	1.16	1.8
36	1.41	1.52	1.35	1.59	1.29	1.65	1.24	1.73	1.18	1.8
37	1.42	1.53	1.36	1.59	1.31	1.66	1.25	1.72	1.19	1.8
38	1.43	1.54	1.37	1.59	1.32	1.66	1.26	1.72	1.21	1.79
39	1.43	1.54	1.38	1.6	1.33	1.66	1.27	1.72	1.22	1.79
40	1.44	1.54	1.39	1.6	1.34	1.66	1.29	1.72	1.23	1.79
45	1.48	1.57	1.43	1.62	1.38	1.67	1.34	1.72	1.29	1.78
50	1.5	1.59	1.46	1.63	1.42	1.67	1.38	1.72	1.34	1.77
55	1.53	1.6	1.49	1.64	1.45	1.68	1.41	1.72	1.38	1.77
60	1.55	1.62	1.51	1.65	1.48	1.69	1.44	1.73	1.41	1.77
65	1.57	1.63	1.54	1.66	1.5	1.7	1.47	1.73	1.44	1.77
70	1.58	1.64	1.55	1.67	1.52	1.7	1.49	1.74	1.46	1.77
75	1.6	1.65	1.57	1.68	1.54	1.71	1.51	1.74	1.49	1.77
80	1.61	1.66	1.59	1.69	1.56	1.72	1.53	1.74	1.51	1.77
85	1.62	1.67	1.6	1.7	1.57	1.72	1.55	1.75	1.52	1.77
90	1.63	1.68	1.61	1.7	1.59	1.73	1.57	1.75	1.54	1.78
95	1.64	1.69	1.62	1.71	1.6	1.73	1.58	1.75	1.56	1.78
100	1.65	1.69	1.63	1.72	1.61	1.74	1.59	1.76	1.57	1.78
150	1.72	1.75	1.71	1.76	1.69	1.77	1.68	1.79	1.66	1.8
200	1.76	1.78	1.75	1.79	1.74	1.8	1.73	1.81	1.72	1.82

$\alpha = .05$										
	k = 6		k = 7		k = 8		k = 9		k = 10	
n	dL	dU	dL	dU	dL	dU	dL	dU	dL	dU
11	0.2	3.01								
12	0.27	2.83	0.17	3.15						
13	0.33	2.7	0.23	2.99	0.15	3.27				
14	0.39	2.57	0.29	2.85	0.2	3.11	0.13	3.36		
15	0.45	2.47	0.34	2.73	0.25	2.98	0.18	3.22	0.11	3.44
16	0.5	2.39	0.4	2.62	0.3	2.86	0.22	3.09	0.16	3.3
17	0.55	2.32	0.45	2.54	0.36	2.76	0.27	2.98	0.2	3.18
18	0.6	2.26	0.5	2.47	0.41	2.67	0.32	2.87	0.24	3.07
19	0.65	2.21	0.55	2.4	0.46	2.59	0.37	2.78	0.29	2.97
20	0.69	2.16	0.6	2.34	0.5	2.52	0.42	2.7	0.34	2.89
21	0.73	2.12	0.64	2.3	0.55	2.46	0.46	2.63	0.38	2.81
22	0.77	2.09	0.68	2.25	0.59	2.41	0.51	2.57	0.42	2.73
23	0.8	2.06	0.72	2.21	0.63	2.36	0.55	2.51	0.47	2.67
24	0.84	2.04	0.75	2.17	0.67	2.32	0.58	2.46	0.51	2.61
25	0.87	2.01	0.78	2.14	0.7	2.28	0.62	2.42	0.54	2.56
26	0.9	1.99	0.82	2.12	0.74	2.24	0.66	2.38	0.58	2.51
27	0.93	1.97	0.85	2.09	0.77	2.22	0.69	2.34	0.62	2.47
28	0.95	1.96	0.87	2.07	0.8	2.19	0.72	2.31	0.65	2.43
29	0.98	1.94	0.9	2.05	0.83	2.16	0.75	2.28	0.68	2.4
30	1	1.93	0.93	2.03	0.85	2.14	0.78	2.25	0.71	2.36
31	1.02	1.92	0.95	2.02	0.88	2.12	0.81	2.23	0.74	2.33
32	1.04	1.91	0.97	2	0.9	2.1	0.84	2.2	0.77	2.31
33	1.06	1.9	0.99	1.99	0.93	2.09	0.86	2.18	0.8	2.28
34	1.08	1.89	1.02	1.98	0.95	2.07	0.89	2.16	0.82	2.26
35	1.1	1.88	1.03	1.97	0.97	2.05	0.91	2.14	0.85	2.24
36	1.11	1.88	1.05	1.96	0.99	2.04	0.93	2.13	0.87	2.22
37	1.13	1.87	1.07	1.95	1.01	2.03	0.95	2.11	0.89	2.2
38	1.5	1.86	1.09	1.94	1.03	2.02	0.97	2.1	0.91	2.18
39	1.16	1.86	1.1	1.93	1.05	2.01	0.99	2.09	0.93	2.16
40	1.18	1.85	1.12	1.92	1.06	2	1.01	2.07	0.95	2.15
45	1.24	1.84	1.19	1.9	1.14	1.96	1.09	2.02	1.04	2.09
50	1.29	1.82	1.25	1.88	1.2	1.93	1.16	1.99	1.11	2.04
55	1.33	1.81	1.29	1.86	1.25	1.91	1.21	1.96	1.17	2.01
60	1.37	1.81	1.34	1.85	1.3	1.89	1.26	1.94	1.22	1.98
65	1.4	1.81	1.37	1.84	1.34	1.88	1.3	1.92	1.27	1.96
70	1.43	1.8	1.4	1.84	1.37	1.87	1.34	1.91	1.31	1.95
75	1.46	1.8	1.43	1.83	1.4	1.87	1.37	1.9	1.34	1.94
80	1.48	1.8	1.45	1.83	1.43	1.86	1.4	1.89	1.37	1.93
85	1.5	1.8	1.47	1.83	1.49	1.86	1.42	1.89	1.4	1.92
90	1.52	1.8	1.49	1.83	1.47	1.85	1.45	1.88	1.42	1.91
95	1.54	1.8	1.51	1.83	1.49	1.85	1.46	1.88	1.44	1.9
100	1.55	1.8	1.53	1.83	1.5	1.85	1.48	1.87	1.46	1.9
150	1.65	1.82	1.64	1.83	1.62	1.85	1.6	1.86	1.59	1.88
200	1.71	1.83	1.7	1.84	1.69	1.85	1.68	1.86	1.67	1.87

Applying the Decision Rules for Hypothesis Testing

Once the Durbin-Watson statistic (d) has been precisely calculated from the [regression residuals](#) and the critical bounds (d_L and d_U) have been correctly ascertained from the appropriate table, the crucial final step involves applying the established decision rules. The primary test is typically focused on detecting **positive autocorrelation** and is based on a one-sided hypothesis test. The [null hypothesis](#) (H_0) asserts that there is no positive autocorrelation (i.e., $\rho \leq 0$), where ρ denotes the population first-order autocorrelation coefficient. The alternative hypothesis (H_A) maintains that positive autocorrelation is present (i.e., $\rho > 0$).

The decision process requires comparing the calculated ' d ' statistic against the bounds d_L and d_U , which effectively partition the statistic's total range into five definitive regions. The results are interpreted as follows:

Strong Evidence of Positive Autocorrelation: If the calculated statistic d is less than the lower bound ($d < d_L$), the null hypothesis (H_0) is definitively rejected. This outcome provides strong statistical evidence that the residuals are positively correlated, signaling a serious model specification error that necessitates corrective action.

Inconclusive Region (Positive): If the statistic falls between the bounds ($d_L \leq d \leq d_U$), the test is considered inconclusive. Within this indeterminate zone, the researcher lacks sufficient statistical power to either definitively reject H_0 or confirm its acceptance. In such cases, researchers may attempt to increase the sample size, utilize more powerful alternative tests, or rely on substantive prior knowledge of the data generating process to make a judicious judgment.

No Positive Autocorrelation: If the calculated statistic d is greater than the upper bound ($d > d_U$), the null hypothesis of no positive autocorrelation is not rejected. In this favorable scenario, the model errors are deemed sufficiently independent for standard [OLS](#) inference to proceed without requiring correction for serial correlation.

Strong Evidence of Negative Autocorrelation: Although the test is primarily designed for positive correlation, negative correlation is tested using the statistic mirrored around the mean of 2, which is $4 - d$. If d is greater than $4 - d_L$, we reject the hypothesis of no negative autocorrelation. This result strongly suggests that the residuals exhibit an alternating pattern in their signs.

Inconclusive Region (Negative): If $4 - d_U \leq d \leq 4 - d_L$, the statistical evidence regarding negative autocorrelation remains inconclusive.

It is important to emphasize that if the calculated ' d ' value lands precisely or very close to 2, the statistic confirms the ideal scenario where the errors are random and statistically independent.

Nevertheless, given the inherent risk of specification errors in most econometric models, encountering the inconclusive region is quite common, particularly when dealing with smaller sample sizes. Researchers facing inconclusive results should consider performing alternative diagnostic tests or meticulously examining residual plots for visual patterns that could reveal the underlying nature of the correlation. The fundamental conclusion remains: falling into the rejection regions for either positive or negative serial correlation signals a critical failure of the independence assumption, thereby invalidating standard [OLS](#) assumptions regarding the variance of the coefficient estimates.

Addressing Limitations and Advanced Testing Methods

While the [Durbin-Watson Test](#) remains a foundational and widely used methodology for detecting first-order autocorrelation, it does possess notable limitations, particularly in the context of advanced modern econometric modeling. The most significant constraint is that the test is designed only to reliably detect **first-order autocorrelation** (the correlation between e_t and e_{t-1}). It is generally ineffective at identifying higher-order serial correlation, such as correlation between e_t and e_{t-2} , which is frequently encountered in seasonal or cyclical data patterns. Furthermore, the test becomes statistically invalid if the regression model incorporates a lagged dependent variable (e.g., Y_{t-1}) as one of the independent predictors. The inclusion of such a variable systemically biases the 'd' statistic toward the center value of 2, thus masking true autocorrelation and leading to false non-rejection of the null hypothesis.

For situations involving potential higher-order autocorrelation or models that necessitate the inclusion of lagged dependent variables, more sophisticated techniques are required. The [Breusch-Godfrey \(BG\) Test](#) is recognized as a more robust and flexible alternative. The BG test operates asymptotically (making it highly suitable for large samples) and possesses the critical ability to test for autocorrelation up to any specified order (p). Crucially, it remains statistically valid even when lagged dependent variables are included in the model specification. Similarly, the [Ljung-Box Q-statistic](#) is widely applied in pure time-series modeling (such as ARIMA models) to test for overall residual autocorrelation across multiple lags simultaneously. These advanced alternatives often provide direct p-values, which eliminates the need for consulting complex critical value tables and navigating the ambiguities of the inconclusive regions.

Despite these known limitations, the Durbin-Watson test maintains its high value as a straightforward, easily calculated initial diagnostic tool, especially since standard statistical software packages automatically compute the 'd' statistic. Its continued relevance is inextricably linked to its effectiveness in rapidly identifying the most common form of serial correlation--the first-order dependence that characterizes many economic and financial time series. By diligently combining the calculated statistic with the critical values provided in the tables above, analysts can quickly and effectively assess the fundamental validity of their [OLS](#) assumptions regarding error

independence, thereby paving the path for more rigorous and reliable statistical inference.